

Audio-Technica Devices

Possible Operation Combination Tables

These compatibility tables are current as of July 2025.

Firmware compatibility tables

ESW-R4180DAN

ESW-R4180DAN <=> ESW-T4101, T4102, T4106, T4107

√: operation checked

-: operation not possible

ESW-R4180DAN	ESW-T4101, T4102, T4106, T4107 firmware version					
firmware version	1.0.5 ^[2]	1.1.0 ^[2]	1.1.1 ^[2]	1.2.0	1.2.1	
1.0.3 ^[1]	✓	_	_	_	_	
1.1.0 ^[1]	_	✓	_	_	_	
1.1.1	_	_	✓	✓	_	
1.1.2	_	_	_	_	✓	

^[1] There is a phenomenon where the receiver and transmitter cannot be connected after 50 days of continuous operation.

ESW-R4180DAN <=> ESW-CHG4/A, CHG5/A

√: operation checked

-: operation not possible

ESW-R4180DAN	ESW-CHG4/A, CHG5/A firmware version				
firmware version	1.0.9 ^[2]	1.1.0 ^[2]	1.1.1	1.2.1	
1.0.3 ^[1]	✓	_	_	_	
1.1.0 ^[1]	_	✓	_	_	
1.1.1	_	_	✓	✓	
1.1.2	_	_	_	✓	

^[1] There is a phenomenon where the receiver and transmitter cannot be connected after 50 days of continuous operation.

ESW-T4101, T4102, T4106, T4107 <=> ESW-CHG4/A, CHG5/A

✓: operation checked

 $[\]label{eq:continuous} \textbf{[2] Rarely, the transmitter may stop turning on when the rechargeable battery parameters are read.}$

^[2] A charging error will occur on the 201st and all subsequent charging operations.

ESW-T4101 ESW-T4102 ESW-T4106	ESW-CHG4/A, CHG5/A firmware version			
ESW-T4100 ESW-T4107 firmware version	1.0.9 ^[2]	1.1.0 ^[2]	1.1.1	1.2.1
1.0.5 ^[1]	✓	_	_	_
1.1.0 ^[1]	_	✓	_	_
1.1.1 ^[1]	_	_	✓	_
1.2.0	_	_	✓	✓
1.2.1	_	_	_	✓

^[1] Rarely, the transmitter may stop turning on when the rechargeable battery parameters are read.

ESW-R4180LK

ESW-R4180LK <=> ESW-T4101, T4102, T4106, T4107

✓: operation checked

—: operation not possible

ESW-R4180LK	ESW-T4101, T4102, T4106, T4107 firmware version					
firmware version	1.0.5 ^[1]	1.1.0 ^[1]	1.1.1 ^[1]	1.2.0	1.2.1	
1.0.0	✓	_	_	_	_	
1.1.0	_	✓	✓	✓	✓	
1.1.1	_	_	_	_	✓	

 $[\]label{eq:continuous} \textbf{[1] Rarely, the transmitter may stop turning on when the rechargeable battery parameters are read.}$

ESW-R4180LK <=> ESW-CHG4/A, CHG5/A

✓: operation checked

—: operation not possible

ESW-R4180LK firmware version	ESW-CHG4/A, CI	ESW-CHG4/A, CHG5/A firmware version			
	1.0.9 ^[1]	1.1.0 ^[1]	1.1.1	1.2.1	
1.0.0	✓	_	_	_	
1.1.0	_	✓	✓	✓	
1.1.1	_	_	_	✓	

^[1] A charging error will occur on the 201st and all subsequent charging operations.

ESW-T4101, T4102, T4106, T4107 <=> ESW-CHG4/A, CHG5/A

✓: operation checked

^[2] A charging error will occur on the 201st and all subsequent charging operations.

ESW-T4101 ESW-T4102 ESW-T4106	ESW-CHG4/A, CHG5/A firmware version			
ESW-T4100 ESW-T4107 firmware version	1.0.9 ^[2]	1.1.0 ^[2]	1.1.1	1.2.1
1.0.5 ^[1]	✓	_	_	_
1.1.0 ^[1]	_	✓	_	_
1.1.1 ^[1]	_	_	✓	_
1.2.0	_	_	✓	✓
1.2.1	_	_	_	✓

^[1] Rarely, the transmitter may stop turning on when the rechargeable battery parameters are read.

ESW-R4180DAN (S-1)

ESW-R4180DAN (S-1) <=> ESW-T4101, T4102, T4106, T4107

✓: operation checked

—: operation not possible

ESW-R4180DAN (S-1)	ESW-T4101, T4102, T4106, T4107 firmware version					
firmware version	1.0.5 ^[1]	1.1.0 ^[1]	1.1.1 ^[1]	1.2.0	1.2.1	
1.0.0	_	✓	✓	✓	✓	
1.0.1	_	_	_	_	✓	

 $^{[1] \} Rarely, the transmitter \ may \ stop \ turning \ on \ when \ the \ rechargeable \ battery \ parameters \ are \ read.$

ESW-R4180DAN (S-1) <=> ESW-CHG4/A, CHG5/A

✓: operation checked

—: operation not possible

ESW-R4180DAN (S-1)	ESW-CHG4/A, CHG5/A firmware version				
firmware version	1.0.9 ^[1]	1.1.0 ^[1]	1.1.1	1.2.1	
1.0.0	✓	✓	✓	✓	
1.0.1	_	_	_	✓	

 $[\]ensuremath{[1]}$ A charging error will occur on the 201st and all subsequent charging operations.

ESW-T4101, T4102, T4106, T4107 <=> ESW-CHG4/A, CHG5/A

√: operation checked

^[2] A charging error will occur on the 201st and all subsequent charging operations.

ESW-T4101 ESW-T4102 ESW-T4106	ESW-CHG4/A, CHG5/A firmware version			
ESW-T4100 ESW-T4107 firmware version	1.0.9 ^[2]	1.1.0 ^[2]	1.1.1	1.2.1
1.0.5 ^[1]	✓	_	_	_
1.1.0 ^[1]	_	✓	_	_
1.1.1 ^[1]	_	_	✓	_
1.2.0	_	_	✓	✓
1.2.1	_	_	_	✓

^[1] Rarely, the transmitter may stop turning on when the rechargeable battery parameters are read.

Application compatibility tables

ESW-R4180DAN

Wireless Manager <=> ESW-R4180DAN

✓: operation checked

Wireless Manager	ESW-R4180I	ESW-R4180DAN firmware version				
application version	1.0.3 ^[1]	1.1.0 ^[1]	1.1.1	1.1.2		
< 2.1.1	_	_	_	_		
2.1.1 ^[2]	✓	_	_	_		
2.2.1 ^[2]	✓	_	_	_		
2.2.2 ^[2]	✓	✓	_	_		
2.2.3 ^[2]	_	✓	_	_		
2.2.4 ^{[2][3]}	_	_	✓	_		
2.2.5 ^[2]	_	_	✓	_		
2.3.0 ^[2]	_	_	✓	_		
2.3.2	_	_	✓	_		
2.3.3	_	_	✓	✓		

^[1] There is a phenomenon where the receiver and transmitter cannot be connected after 50 days of continuous operation.

^[2] A charging error will occur on the 201st and all subsequent charging operations.

^[2] Wireless Manager cannot update the firmware of the ESW-CHG4/A or ESW-CHG5/A over a network.

^[3] When you execute "Max Channel Calculation," you will exit Wireless Manager.

Wireless Manager <=> ESW-T4101, T4102, T4106, T4107

✓: operation checked

-: operation not possible

Wireless Manager	ESW-T4101, T4102, T4106, T4107 firmware version					
application version	1.0.5 ^[1]	1.1.0 ^[1]	1.1.1 ^[1]	1.2.0	1.2.1	
< 2.1.1	_	_	_	_	_	
2.1.1 ^[2]	✓	_	_	_	_	
2.2.1 ^[2]	✓	_	_	_	_	
2.2.2 ^[2]	✓	✓	_	_	_	
2.2.3 ^[2]	_	✓	_	_	_	
2.2.4 ^{[2][3]}	_	_	✓	_	_	
2.2.5 ^[2]	_	_	✓	_	_	
2.3.0 ^[2]	_	_	✓	_	_	
2.3.2	_	_	_	✓	_	
2.3.3	_	_	_	✓	✓	

^[1] Rarely, the transmitter may stop turning on when the rechargeable battery parameters are read.

Wireless Manager <=> ESW-CHG4/A, CHG5/A

✓: operation checked

Wireless Manager	ESW-CHG4/A, CHG5/A firmware version				
application version	1.0.9 ^[1]	1.1.0 ^[1]	1.1.1	1.2.1	
< 2.1.1	_	_	_	_	
2.1.1 ^[2]	✓	_	_	_	
2.2.1 ^[2]	✓	_	_	_	
2.2.2 ^[2]	✓	✓	_	_	
2.2.3 ^[2]	_	✓	_	_	
2.2.4 ^{[2][3]}	_	_	✓	_	
2.2.5 ^[2]	_	_	✓	_	
2.3.0 ^[2]	_	_	✓	_	
2.3.2	_	_	✓	✓	
2.3.3	_	_	_	✓	

^[1] A charging error will occur on the 201st and all subsequent charging operations.

 $[\]label{thm:choice} \ensuremath{\text{[2]}} \ensuremath{\text{Wireless Manager cannot update the firmware of the ESW-CHG4/A or ESW-CHG5/A over a network.}$

^[3] When you execute "Max Channel Calculation," you will exit Wireless Manager.

- [2] Wireless Manager cannot update the firmware of the ESW-CHG4/A or ESW-CHG5/A over a network.
- [3] When you execute "Max Channel Calculation," you will exit Wireless Manager.

ESW-R4180LK

Wireless Manager <=> ESW-R4180LK

✓: operation checked

-: operation not possible

Wireless Manager application version	ESW-R4180LK firmware version		
	1.0.0	1.1.0	1.1.1
< 2.2.2	_	_	_
2.2.2 ^[1]	✓	✓	_
2.2.3 ^[1]	_	✓	_
2.2.4 ^{[1][2]}	_	✓	_
2.2.5 ^[1]	_	✓	_
2.3.0 ^[1]	_	✓	_
2.3.2	_	✓	_
2.3.3	_	✓	✓

^[1] Wireless Manager cannot update the firmware of the ESW-CHG4/A or ESW-CHG5/A over a network.

Wireless Manager <=> ESW-T4101, T4102, T4106, T4107

✓: operation checked

Wireless Manager application version	ESW-T4101, T4102, T4106, T4107 firmware version				
	1.0.5 ^[1]	1.1.0 ^[1]	1.1.1 ^[1]	1.2.0	1.2.1
< 2.1.1	_	_	_	_	_
2.1.1 ^[2]	✓	_	_	_	_
2.2.1 ^[2]	✓	_	_	_	_
2.2.2 ^[2]	✓	✓	_	_	_
2.2.3 ^[2]	_	✓	_	_	_
2.2.4 ^{[2][3]}	_	_	✓	_	_
2.2.5 ^[2]	_	_	✓	_	_
2.3.0 ^[2]	_	_	✓	_	_
2.3.2	_	_	_	✓	_
2.3.3	_	_	_	✓	✓

^[2] When you execute "Max Channel Calculation," you will exit Wireless Manager.

- [1] Rarely, the transmitter may stop turning on when the rechargeable battery parameters are read.
- $\label{thm:choice} \ensuremath{\text{[2]}} \ensuremath{\text{Wireless Manager cannot update the firmware of the ESW-CHG4/A or ESW-CHG5/A over a network.}$
- [3] When you execute "Max Channel Calculation," you will exit Wireless Manager.

Wireless Manager <=> ESW-CHG4/A, CHG5/A

✓: operation checked

—: operation not possible

Wireless Manager application version	ESW-CHG4/A, CHG5/A firmware version			
	1.0.9 ^[1]	1.1.0 ^[1]	1.1.1	1.2.1
< 2.1.1	_	_	_	_
2.1.1 ^[2]	✓	_	_	_
2.2.1 ^[2]	✓	_	_	_
2.2.2 ^[2]	✓	✓	_	_
2.2.3 ^[2]	_	✓	_	_
2.2.4 ^{[2][3]}	_	_	✓	_
2.2.5 ^[2]	_	_	✓	_
2.3.0 ^[2]	_	_	✓	_
2.3.2	_	_	✓	✓
2.3.3	_	_	_	✓

^[1] A charging error will occur on the 201st and all subsequent charging operations.

ESW-R4180DAN (S-1)

Wireless Manager <=> ESW-R4180DAN (S-1)

√: operation checked

^[2] Wireless Manager cannot update the firmware of the ESW-CHG4/A or ESW-CHG5/A over a network.

^[3] When you execute "Max Channel Calculation," you will exit Wireless Manager.

Wireless Manager application version	ESW-R4180DAN (S-1) firmware version		
	1.0.0	1.0.1	
< 2.1.1	_	_	
2.1.1 ^[1]	✓	_	
2.2.1 ^[1]	✓	_	
2.2.2 ^[1]	✓	_	
2.2.3 ^[1]	✓	_	
2.2.4 ^{[1][2]}	✓	_	
2.2.5 ^[1]	✓	_	
2.3.0 ^[1]	✓	_	
2.3.2	✓	_	
2.3.3	✓	✓	

^[1] Wireless Manager cannot update the firmware of the ESW-CHG4/A or ESW-CHG5/A over a network.

Wireless Manager <=> ESW-T4101, T4102, T4106, T4107

✓: operation checked

Wireless Manager	ESW-T410	ESW-T4101, T4102, T4106, T4107 firmware version			
application version	1.0.5 ^[1]	1.1.0 ^[1]	1.1.1 ^[1]	1.2.0	1.2.1
< 2.1.1		_	_	_	_
2.1.1 ^[2]	✓	_	_	_	_
2.2.1 ^[2]	✓	_	_	_	_
2.2.2 ^[2]	✓	✓	_	_	_
2.2.3 ^[2]	_	✓	_	_	_
2.2.4 ^{[2][3]}	_	_	✓	_	_
2.2.5 ^[2]	_	_	✓	_	_
2.3.0 ^[2]	_	_	✓		_
2.3.2	_	_	_	✓	_
2.3.3	_	_	_	✓	✓

^[1] Rarely, the transmitter may stop turning on when the rechargeable battery parameters are read.

^[2] When you execute "Max Channel Calculation," you will exit Wireless Manager.

 $[\]label{eq:constraint} \ensuremath{\text{[2]}} \ensuremath{\text{Wireless Manager cannot update the firmware of the ESW-CHG4/A or ESW-CHG5/A over a network.}$

 $[\]hbox{[3] When you execute "Max Channel Calculation," you will exit Wireless Manager.}\\$

Wireless Manager <=> ESW-CHG4/A, CHG5/A

✓: operation checked

-: operation not possible

Wireless Manager application version	ESW-CHG4/A, CH	ESW-CHG4/A, CHG5/A firmware version			
	1.0.9 ^[1]	1.1.0 ^[1]	1.1.1	1.2.1	
< 2.1.1	_	_	_	_	
2.1.1 ^[2]	✓	_	_	_	
2.2.1 ^[2]	✓	_	_	_	
2.2.2 ^[2]	✓	✓	_	_	
2.2.3 ^[2]	_	✓	_	_	
2.2.4 ^{[2][3]}	_	_	✓	_	
2.2.5 ^[2]	_	_	✓	_	
2.3.0 ^[2]	_	_	✓	_	
2.3.2	_	_	✓	✓	
2.3.3		_	_	✓	

^[1] A charging error will occur on the 201st and all subsequent charging operations.

IP control protocol specification compatibility tables

ESW-R4180DAN

Specification	Firmware version	Firmware version			
version	ESW-R4180DAN	ESW-T4101, T4102, T4106, T4107	ESW-CHG4/A, CHG5/A		
Ver.1	1.0.3	1.0.5	1.0.9		
	1.1.0	1.1.0	1.1.0		
Ver.2	1.1.1	1.1.1	1.1.1		
	1.1.2	1.2.1	1.2.1		

 $[\]label{thm:choice} \ensuremath{\text{[2]}} \ensuremath{\text{Wireless Manager cannot update the firmware of the ESW-CHG4/A or ESW-CHG5/A over a network.}$

^[3] When you execute "Max Channel Calculation," you will exit Wireless Manager.

ESW-R4180LK

Specification	Firmware version			
version	ESW-R4180LK	ESW-T4101, T4102, T4106, T4107	ESW-CHG4/A, CHG5/A	
Ver.1	1.0.0	1.0.5	1.0.9	
Ver.2	1.1.0 1.1.1	1.1.0 1.1.1 1.2.1	1.1.0 1.1.1 1.2.1	

ESW-R4180DAN (S-1)

Specification	Firmware version				
Specification version	ESW-R4180DAN (S- 1)	ESW-T4101, T4102, T4106, T4107	ESW-CHG4/A, CHG5/A		
Ver.1	_	1.0.5	1.0.9		
Ver.2	1.0.0	1.1.0 1.1.1 1.2.1	1.1.0 1.1.1 1.2.1		

Audio-Technica LINK Devices

These compatibility tables are current as of July 2025.

ESW-R4180LK

ESW-R4180LK <=> ATDM-1012

✓: operation checked

-: operation not possible

ATDM-1012	ESW-R4180LK firmware version		
firmware version	1.0.0	1.1.0	1.1.1
< 2.1.2	_	_	_
2.1.2	✓	✓	_
2.2.0	_	✓	_
2.2.1	_	✓	_
2.2.2	_	✓	✓

ESW-R4180LK <=> ATDM-0604a

✓: operation checked

ATDM-0604a	ESW-R4180LK firmware version		
firmware version	1.0.0	1.1.0	1.1.1
< 1.1.2	_	_	_
1.1.2	✓	✓	_
1.2.0	_	✓	_
1.2.1	_	✓	✓